# **Georeferencing Images for use in GPlates**

Authors: Serena Yeung EarthByte Research Group, School of Geosciences, University of Sydney, Australia

#### **Georeferencing Images for use in GPlates**

<u>Aim</u>

**Background** 

Included data

Exercise 1 – Georeferencing the Lord Howe Rise and importing it into GPlates

Exercise 2 – Georeferencing East Antarctica using a polar projection and importing it into GPlates

<u>References</u>

# Aim

This tutorial aims to teach the user how to (1) georeference an image from a paper using ArcGIS 10.1, (2) import the georeferenced image into GPlates and (3) know how to deal with images which do not suit geographic coordinate systems, such as polar areas.

## Background

Georeferencing involves using geographic map coordinates to assign a spatial location to a map feature, such as an image from a scientific paper. GPlates can import a georeferenced image as a raster and correctly place it on the globe and its coastlines, provided that we include the extent of the raster in degrees (latitude and longitude). This is simple to obtain if the map layer you are georeferencing to uses a geographic coordinate system which employs latitude and longitude, such as WGS 1984.

It becomes particularly problematic however if you wish to georeference an image which better suits a projected coordinate system, as these do not employ latitude and longitude. This is the case when working with images located in extreme latitudes, such as in polar areas. It is very difficult trying to georeference a map of Antarctica if the base map layer is not in a polar projection, causing the poles to be compressed, elongated and very hard to match up to.

This tutorial focuses on how to produce georeferenced images in ArcGIS 10.1 which meet the requirements of being able to be imported into GPlates as a raster. Note that other versions of ArcGIS should also work. This tutorial will also run through how to deal with map projections which do not employ latitude and longitude. This tutorial is not designed to teach users how to georeference images in ArcGIS, and assumes a basic knowledge of how to do so. If you require instructions on how to georeference, refer to this YouTube tutorial <<u>http://www.youtube.com/watch?v=PHtxbpboDro</u>> or this ArcGIS webpage <<u>http://help.arcgis.com/en/arcgisdesktop/10.0/help/index.html#//009t0000</u>

#### 00mq000000>

### Included data

<u>Click here</u> to download the data bundle for this tutorial.

This tutorial includes a dataset comprised of two separate folders:

(1) files for the ArcGIS portion of the tutorial

GoodgeFinnAeromagneticsAntarctica.png

NorvickLordHoweRise.png

Seton\_etal\_ESR2012\_Coastline\_2012.1\_polyline.dbf

Seton\_etal\_ESR2012\_Coastline\_2012.1\_polyline.prj

Seton\_etal\_ESR2012\_Coastline\_2012.1\_polyline.shp

Seton\_etal\_ESR2012\_Coastline\_2012.1\_polyline.shx

(2) files for the GPlates portion of the tutorial

Global\_EarthByte\_GPlates\_PresentDay\_StaticPlatePolygons\_20110622 .gpml

Seton\_etal\_ESR2012\_2012.1.rot

Seton\_etal\_ESR2012\_Coastline\_2012.1.gpml

This tutorial dataset is compatible with GPlates 1.5.

# Exercise 1 – Georeferencing the Lord Howe Rise and importing it into GPlates

Any raster image can be georeferenced. When obtaining figures from papers, you can either save an image of the figure directly, or take a screenshot and use an image editing program to save it.

In this exercise we will georeference a PNG image of the Lord Howe Rise (Norvick, 2008) which is included in the tutorial dataset (NovickLordHoweRise.png).

But firstly, load the Seton et al. 2012 Coastlines shapefile (Seton\_etal\_ESR2012\_Coastline\_2012.1\_polyline) into ArcMap using the 'Add Data' button.

This coastlines shapefile will be used to check the alignment of our image once we begin to georeference it.

Note that the coastlines should not be used as the basis for georeferencing your image. They should only be used in this way if the number of known latitudes and longitudes provided in the original raster image are of an insufficient number. That is, where possible, always 'Input DMS of Lon and Lat' when creating control points, rather than matching control points to coastlines.

Change the symbology of the Seton Coastline layer in the Properties window so that the outline is black and a width of 2.0 for ease in distinguishing between the Coastline and the raster image to be georeferenced.

Then, load the raster image 'NovickLordHoweRise.png' into ArcMap.

Use the Georeferencing toolbar to start adding control points to the ungeoreferenced Lord Howe Rise layer. Input the DMS of latitude and longitude of each control point. Refer to the coastlines to check how accurate your georeferencing is.

You may need to match some control points to the coastlines if you do not have enough.

You may also need to transform the layer so that it better fits the coastlines. Try using a  $2^{nd}$  order polynomial transformation.

If you are unsure of how to do these georeferencing steps in ArcGIS, refer to this YouTube tutorial <<u>http://www.youtube.com/watch?v=PHtxbpboDro</u>>

Your final image should look something like this (Figure 1):



**Figure 1.** Georeferenced image of the Lord Howe Rise, transformed using a 2nd order polynomial. Coastline file is in black.

Rectify the image and save it as a TIFF file. While not necessary, specify the Resample Type as Bilinear Interpolation (for continuous data). You may also wish to add `\_rectify' to the end of the filename (NovickLordHoweRise\_rectify) to differentiate it from the original ungeoreferenced image layer.

Change the value of the 'NoData as' field from 256 to 0. If left as 256, ArcGIS will export the image as a black box.

Specify the output location and click Save (Figure 2).

Cell Size:		0.05	0045		
NoData as:		0			
Resample	Type:	Biline	ear Interpolation (for co	ontinuou:	s data) 🔻
Output Lo	cation:	D:\Ja	ames\3.3-New Data		
Name:	NorvickLordHo	weRise	Format:	TIFF	-
Compressi	on Type: NONE	•	Compression Quality (1-100):		75

**Figure 2.** Rectify the image of the Lord Howe Rise. In the Save As window, specify the resample type, filename and export format, then click Save.

(Note: The format box appears grey when the 'Save As' window is opened. In order to change the format to a TIFF file, we need to specify the 'Output Location'. Click on the folder icon next to 'Output Location', and highlight the folder we would like to save the new georeferenced file in. Then click 'Add', and this should allow us to specify the correct format.)

We can now import the rectified, georeferenced image as a raster into GPlates. In order to complete the import stage however, GPlates requires the Extent of the raster in degrees (latitude and longitude).

In order to obtain this information, load the rectified, georeferenced TIFF image into ArcGIS using the 'Add Data' button. Right click on the georeferenced layer (NovickLordHoweRise\_rectify) and select Properties. Click on the 'Source' tab and scroll down to the heading 'Extent', where you will find Top, Left, Right and Bottom coordinates in degrees (Figure 3). These are the coordinates we will enter straight into GPlates.

ieneral	Source	Key Metadata	Extent	Display	Symbology	
Proper	ty		1	/alue		*
1	Status		F	Permanent		
🗆 E	xtent					
	Тор		2	18.044046	53183	
	Left		1	144.51805	0957	-
	Right			177.06674	2613	
-	Bottom		2	45.511406	54303	
E 5	patial Ref	ference	(	GCS_WGS_	_1984	
	Linear Unit					
	Angular Uni	it	1	Degree (0.	0174532925199433)	Ŧ
Data S	Source					
Data Fold Geor Rast	a Type: er: referencing ter:	File ل\:Images_for_u Norv	System ames\3 se_in_G vickLord	Raster .3-Georefe iPlates\Arc HoweRise.	erencing_Images_for_use_in_GPlates\3.3- GIS\ png	*

**Figure 3.** Latitudinal and longitudinal extent of the georeferenced Lord Howe Rise raster, viewed under the Source tab in the Layer Properties window.

Open GPlates and load the following included Coastline, Static Plate Polygon and rotation files using 'Open Feature Collection' (Figure 4).

Seton\_etal\_ESR2012\_Coastline\_2012.1.gpml

Global\_EarthByte\_GPlates\_PresentDay\_StaticPlatePolygons\_20110622

Seton\_etal\_ESR2012\_2012.1.rot



**Figure 4.** GPlates with the Seton coastlines, Earthbyte Static Plate Polygons and the Seton rotation file loaded.

We will now load the georeferenced image (NovickLordHoweRise\_rectify) into GPlates as a raster file. Select 'File', 'Import', and 'Import Raster'.

Navigate to where your image is saved, select the image and click 'Open'. In the first Import Raster window, leave the band name as the default (band\_1) and click Next.

In the second Import Raster window, under Georeferencing, you are prompted to specify the location of the raster. Switch back to ArcGIS where you have the Properties window open and transfer the Top, Left, Right and Bottom coordinates straight into GPlates (Figure 5). Click Next.

G Import	Raster		Gene	ral Source Key Metadata	Extent Display Symbology		
			Pro	perty	Value		*
eoreiere	ncing			Тор	-18.0440463183		
becify the ex	tent of the raster using lat-lo	n bounds or an affine transformation.		Left	144.518050957		
Top (lat)	10.04400			Right	177.066742613		_
Top (lat).	-10.0440-			Bottom	-45.5114064303		
ottom (lat):	-45.5114°			Spatial Reference	GCS_WGS_1984		E
Left (lon):	144.5180°			Linear Unit	Deeree (0.017452202510043	2)	
Right (lon):	177.0667°			Datum	D WGS 1984	5)	_
			E	Statistics	0_000_001		+
			Dat	ta Source			10000
🗍 Show affin	e transform parameters (adv al Extents	anced)	D F G R	Nata Type: File older: D:\J eoreferencing_Images_for_u aster: Non	System Raster ames\3.3-Georeferencing_Images_f se_in_GPlates\ArcGIS\ ickLordHoweRise.png	or_use_in_GPlates\3.3-	*
						Set Data Source	

**Figure 5.** Enter in the coordinates specified in the Extent of the raster in ArcGIS straight into the Georeferencing window in GPlates, ensuring that Top, Left, Right and Bottom are in the correct order.

In the third Import Raster window, under Feature collection, keep the default < Create a new feature collection > option and click Finish. You will now see your raster placed correctly on the globe. Centre the view on eastern Australia and New Zealand and you should see your image. Notice how the coastlines of the Seton et al model match the coastlines of your image. To see the matching coastlines more clearly, change the colour of the Seton coastlines to black using 'Manage Colouring'.

**Note**: if the image appears black in GPlates, or the colour appears odd, check the folder in which your rectified image was saved. If it is black/oddly coloured too, this means that ArcGIS exported the rectified image incorrectly. Ensure that the value of the 'NoData as' field in the Rectify window is 0, not 256. If left as 256, ArcGIS will export the image as a 'black box'.

If this fails to work, you may have to experiment with different output types when rectifying your image in ArcGIS (e.g. TIFF, JPG). We have found that georeferencing a GIF and then rectifying it as PNG works. Import the image as a raster in GPlates as specified above, and you should see your image displayed correctly (Figure 6).



**Figure 6.** Load the raster of the Lord Howe Rise into GPlates and you will see your georeferenced image placed correctly on the globe. To see the matching coastlines more clearly, change the colour of the Seton coastlines to black using `Manage Colouring'.

We will now connect the georeferenced image to the static plate polygon file. This allows the image to reconstruct correctly through time. Notice that if you try reconstructing to say 20 Ma, the image stays put relative to the movement of the plates.

To connect the image to the plate polygons, expand the raster file in the Layers window by clicking on the triangle beside the file name. Under 'Reconstructed polygons:', click 'Add new connection' and select the static polygon file

(Global\_EarthByte\_GPlates\_PresentDay\_StaticPlatePolygons\_20110622.gpml) (Figure 7).

Ad	d new laver
	Cotton attal ECP2012 2012 1
	Reconstruction Tree
	C 4
0	Seton_etal_ESK2012_StaticPolygons_2012.1 Reconstructed Geometries
	Seton_etal_ESR2012_Coastline_2012.1
	Reconstructed Geometries
1	NorvickLordHoweRise_Rectify
-	Reconstructed Raster
•	Inputs
	Raster feature:
	NorvickLordHoweRise_Rectify.gpml =
	Add new connection
	Add new connection
	Ag Seton etal ESR2012 Coastline 2012.1
	Seton etal ESR2012 StaticPolygons 2012.1
	Sufrace relier raster.
	Add new connection
•	Raster options
	Band: band 1
	Onacity: 100 Intensity: 100
	Surface relief scale: 1.00
•	Manage layer

**Figure 7.** In order for the Lord Howe Rise raster to reconstruct correctly through time, connect the Lord Howe Rise raster to the Seton Static Polygons in the Layers window by clicking 'Add new connection'.

Notice that now if you reconstruct through time, such as to 20 Ma, the raster will stay attached to the plate polygons (Figure 8).



**Figure 8.** Once the raster is connected to the static plate polygons, the Lord Howe Rise raster will stay attached to the plate polygons when you reconstruct through time, such as to 20 Ma.

You have now learnt how to georeference images in ArcGIS for use in GPlates!

# **Exercise 2 – Georeferencing East Antarctica using a polar projection and importing it into GPlates**

When georeferencing images located in the extreme latitudes such as polar

areas, it is much easier to use a projected coordinate system rather than a geographic coordinate system. Geographic coordinate systems such as WGS 1984 tend to compress and elongate the poles, making it very difficult to visualise and add control points.

To prepare a georeferenced image that can be imported straight into GPlates, we must ensure that the georeferenced image is saved in a format which uses latitude and longitude. Hence, the best way to go about this is to georeference the image using a polar stereographic projection, but prior to rectifying the image, the projection should be changed back to WGS 1984 to ensure the output is in latitude and longitude.

To do this, load the image to be georeferenced into ArcGIS using the 'Add Data' button. In this exercise we will georeference a PNG image of East Antarctica (Goodge and Finn 2010) which is included in the tutorial dataset (GoodgeFinnAeromagneticsAntarctica).

Change the dataframe's coordinate system by right-clicking 'Layers' in the Table Of Contents window and selecting 'Properties' (Figure 8).



**Figure 8.** In order to reference an image using a different coordinate system, right click 'Layers' in the Table of Contents, and select 'Properties'.

This will open the Data Frame Properties window. Under the 'Coordinate System' tab, scroll down and expand the 'Projected Coordinate Systems' folder, expand the 'Polar' folder and select 'WGS 1984 Antarctic Polar Stereographic'. Click OK (Figure 9).

Feature Cache	Annotation Grou	ups Extent Indicator	rs Frame	Size and Position
General	Data Frame	Coordinate System	Illuminatio	n Grids
-				
	lype here to search	n 🔻	9 2 6	X
	UPS North			*
	UPS South			
	WGS 1984 An	tarctic Polar Stereog	raphic	
	WGS 1984 Ar	ctic Polar Stereograp	hic	
	WGS 1984 Au	istralian Antarctic Lai	mbert	
	WGS 1984 Au	istralian Antarctic Po	lar Stereograph	ic
	WGS 1984 EA	SE Grid North		
	WGS 1984 EA	SE Grid South	1915	
	WGS 1984 IB0	CAO Polar Stereograp	ohic	-
	KITSA IMIGEC 1004 NIA	ath Dolo I AEA Alack		
Current coor	dinate system:			and the second s
WGS_1984	_Antarctic_Polar_Si	tereographic		<u>^</u>
WRID: 505.	Addionty: EP36			
Projection:	Stereographic_Sou	ith_Pole		E
False_Eastin	ng: 0.0			
Central Me	ridian: 0.0			
Standard_P	arallel_1: -71.0			
Linear Unit:	Meter (1.0)			
Geographic	Coordinate System	n: GCS_WGS_1984		-
Transform	ations			
Tanatom	indorisi i			

**Figure 9.** Select the WGS 1984 Antarctic Polar Stereographic projection system in the Data Frame Properties window, then press OK.

You will now be able to see Antarctica much more clearly in this polar projection. Start to georeference the image by adding control points as before using the Georeferencing toolbar (Figure 10).

In this circumstance, you will mostly likely need to match all control points to the coastline file. There will not be enough control points to 'Input DMS of Lon and Lat'.

You may not find it necessary to transform it from a 1<sup>st</sup> Order Polynomial to a 2<sup>nd</sup> Order Polynomial. Once you have finished georeferencing, click 'Update Georeferencing' in the drop-down menu of your Georeferencing toolbar.



**Figure 10.** Add control points in order to georeference the of Antarctica onto the map coordinates of the Seton coastlines.

Change the data frame's coordinate system back to the global coordinate

system WGS 1984 by right clicking 'Layers' and selecting 'Properties'. Scroll down and expand the last folder named 'Layers' and select 'GCS\_WGS\_1984'. Click OK (Figure 11).

Feature Cache	Annotation Groups	Extent Indicators	Frame	Size and Position
General	Data Frame C	oordinate System	Illuminat	ion Grids
<b>T</b>	ype here to search	• @	8	- 🔆
⊕ 🚰 Pro	<ul> <li>NSWC 9Z-2</li> <li>WGS 1966</li> <li>WGS 1972</li> <li>WGS 1972 TBE</li> <li>WGS 1984</li> <li>jected Coordinate Sy</li> </ul>	stems		*
	ers GCS_WGS_1984 WGS_1984_Antarctic	_Polar_Stereographi	c	E .
Current coord	dinate system:			
GCS_WGS_1 WKID: 4326 Angular Unit Prime Meridi: Datum: D_W Spheroid: \ Semimajor Semiminor Inverse F	1984 Authority: EPSG an: Greenwich (0.0) /GS_1984 WGS_1984 r Axis: 6378137.0 r Axis: 6356752.31424 lattening: 298.257223	25199433) 5179 563		*
Transform	ations			

**Figure 11.** Change the data frame's coordinate system back to WGS 1984 in the Data Frame Properties window, which can be opened by right clicking 'Layers' in the Table of Contents window and selecting 'Properties'.

Your georeferenced image of Antarctica should look stretched out, but be in the correct spot (Figure 12).



**Figure 12.** The georeferenced image of East Antarctica in projected using the geographic coordinate system WGS 1984.

If your image of Antarctica turned into a block colour and is stretched out over the entire frame of your GCS WGS 1984 projection, this means that you did not 'Update Georeferencing' while in the Antarctic Polar Stereographic projection. Return to the Polar projection, click 'Update Georeferencing' under the drop-down 'Georeferencing' button, then return to the Geographic coordinate system.

Unlike the previous example, we cannot 'Rectify' the image of Antarctica when it is displayed in a projection other than the one it was originally georeferenced to. Since we require latitude and longitude in the Geographic coordinate system, this becomes a problem.

One alternative way is to export the image as a raster.

Right click the Antarctic image layer in the Table Of Contents window, and under 'Data', select 'Export Data...' (Figure 13).





In the Export Raster Data window which opens, change the Spatial

Reference to 'Data Frame (Current)'. Notice that the Extent in the attribute table will change accordingly.

Select a suitable Location to save to by clicking the folder button, specify the name (e.g. GoodgeFinnAeromagneticsAntarctica\_WGS1984) and change the format to PNG.

Change the value of the 'NoData as' field from 252 to 0. If left as 252, ArcGIS will export the image as a 'black box'.

port Raster Data - GoodgeFinnA	AeromagneticsAntarc	tica.png		
Extent Data Frame (Current) Raster Dataset (Original) Selected Graphics (Clipping)	Clip Inside	Spatial Reference	e (Current) set (Original)	
Output Raster	Square: Ce	ell Size (cx, cy): )	0.1474282970	0.1472314134
Force RGB	Raster <mark>Size (</mark>	columns, rows): 🔘	2442	190
Use Colormap		NoData as:	0	
Name	Property			
Bands Pixel Depth Uncompressed Size Extent (left, top, right, bottom	3 8 Bit 1.33 MB ) (-180.0000, -62	2.0130, 180.0000, -	90.0000 )	H
•	III			•
Location:	D:\James\3.3-Georef	erencing_Images_fo	or_use_in_GPlates	3.3-Ger 🔁
Name:	GoodgeFinnAeroma	Format:	PNG	•
Compression Type:	LZ77 -	Compression Qual (1-100):	ity 75	
About export raster data		Save		Cancel

Click Save (Figure 14).

**Figure 14.** In the Export Raster Data window, change the Spatial Reference to 'Data Frame (Current)'. Specify a file location, name and format, then click Save.

Load your newly exported data into ArcGIS by using the 'Add Data' button. Right click the layer, select Properties, and scroll down to the 'Extent' and 'Spatial Reference' information. Notice that the spatial reference is now GCS\_WGS\_1984 and not the polar projection, and that the extent is in

latitude and	longitude	(Figure 15).
--------------	-----------	--------------

onordi	Source	Key Metadata	Extent	Display	Symbology	
Proper	ty		v	alue		
	Status		P	ermanent		
E	xtent					
1	Гор		-(	52.013029	90068	
1	eft		-	180		
1	Right		1	80.01990	1274	=
1	Bottom		-1	89.986997	75718	
E 5	patial R	eference	G	CS_WGS_	_1984	
1	inear Uni	t				
	Angular U	nit	D	egree (0.	0174532925199433)	-
Data S	ource					
Data	Type: er: eferencin er:	File D:\; g_Images_for_u Goo	System F lames\3. se_in_GF dgeFinn/	Raster 3-Georefe Plates\Arc Aeromagn	erencing_Images_for_use_in_GPlates\3.3- :GIS\ ieticsAntarctica1.png	*
Geor Rast						-

**Figure 15.** Latitudinal and longitudinal extent of the georeferenced East Antarctica raster, viewed under the Source tab in the Layer Properties window.

You are now ready to load the image into GPlates!

Open GPlates and load the following included Coastline, Static Plate Polygon and rotation files using 'Open Feature Collection' if you haven't already.

Seton\_etal\_ESR2012\_Coastline\_2012.1.gpml

Global\_EarthByte\_GPlates\_PresentDay\_StaticPlatePolygons\_20110622

Seton\_etal\_ESR2012\_2012.1.rot

We will now load the georeferenced image

(GoodgeFinnAeromagneticsAntarctica\_WGS1984) into GPlates as a raster file. Select 'File', 'Import', and 'Import Raster'. Navigate to where your image is saved, select the image and click 'Open'.

Import the raster as you did using the Lord Howe Rise example. If you are prompted to specify an age of the raster in the first import window, type 0 (0 Ma). In the next few windows, keep all defaults except the georeferencing coordinates. Type in the latitudes and longitudes of your Antarctic image straight from the 'Extent' section in your Layer Properties box from ArcGIS (Figure 16).

G Import			
	Raster		
Georetere	ncing		
Specify the ex	tent of the raster using lat-lo	on bounds or an affine transformation.	
Top (lat):	62.0130°	-	
Bottom (lat):	-89.9869°		
Left (lon):	-180.0000°	<b></b>	
Right (lon):	180.0199°	×	
		0	

**Figure 16.** Use 'Import Raster' to import the georeferenced East Antarctica raster into GPlates. Enter in the coordinates specified in the Extent of the raster in ArcGIS into the GPlates Georeferencing window.

Create a new feature collection and click 'Create'.

Centre your globe on Antarctica and you should see your image in the correct location (Figure 17). Ensure that the reconstruction time is reset to 0 Ma from the previous exercise.



**Figure 17.** Your imported georeferenced raster of East Antarctica should be placed correctly on the globe. Ensure that the reconstruction time is reset to 0 Ma from the previous exercise.

**Note once more**: if the image appears black in GPlates, or the image appears odd in colour, ArcGIS exported the rectified image incorrectly. Change the value of the 'NoData as' field in the Rectify window from 252 to 0. If this fails to work, georeferencing a GIF and then exporting it as PNG

works. Import the image as a raster in GPlates as specified above, and you should see your image displayed correctly.

We will now connect the georeferenced image to the static plate polygon file. This allows the image to reconstruct correctly through time. Notice that if you try reconstructing to say 20 Ma, the image stays put relative to the movement of the plates.

Connect the Antarctic image to the static plate polygons in GPlates as you did in the previous exercise. Expand the raster file in the Layers window by clicking on the triangle beside the file name. Under 'Reconstructed polygons:', click 'Add new connection' and select the static polygon file (Seton\_etal\_ESR2012\_StaticPolygons\_2012.1).

Notice that now if you reconstruct through time, the raster will stay attached to the plate polygons.

You have now learnt how to georeference polar images in ArcGIS for use in GPlates!

## References

Goodge, J.W. and Finn, C.A. 2010. Glimpses of East Antarctica: Aeromagnetic and satellite magnetic view from the central Transantarctic Mountains of East Antarctica. *Journal of Geophysical Research* 115

Norvick, M.S., Langford, R.P., Hashimoto, T., Rollet, N., Higgins, K.L. and Morse, M.P. 2008. New insights into the evolution of the Lord Howe Rise (Capel and Faust basins), offshore eastern Australia, from terrane and geophysical data analysis. In: Eastern Australasian Basins Symposium III: Energy security for the 21st century, Blevin, J.E., Bradshaw, B.E. and Uruski, C. eds. Petroleum Exploration Society of Australia Special Publication: 291–310